DPU121226 Protocol.doc

Medi SMARTS

PC to DPU SET PARAMETER

THR

0	1-2	3-4	5	6	7-11	12	13
01	39	dpu #	30	Exp.	Mantissa	Cs	04

BackGround

0	1-2	3-4	5	6	7-11	12	13
01	39	dpu #	32	Exp.	Mantissa	Cs	04

CLR DOSE or TOTAL

0	1-2	3-4	5	6	7	8-10	11	12	13
01	39	dpu #	*	*	2D	30	31	Cs	04

CAL BackGround

<u> </u>									
0	1-2	3-4	5	6	7	8-10	11	12	13
01	39	dpu #	*	*	2D	30	32	Cs	04

DPU to PC Threshold ACK &. Back Ground ACK. & Clear Dose or Total

ACK.&

Cal Back-Ground Ack

0	1 – 2	3 – 4	5	6-10	11	12-14	15-16	17	18
01	dpu #	39	31	Rx6-	Rx11	73,74,6	30	С	04
				Rx10	if BacG=33	1		S	
						sta			

<u>BackGround</u> or Thr Mantissa (7-11) = *10000 + *1000 + *100 + *100 + *10 + *10 + *10 + *10Exp(6)=> 31H=/10, 32H=/100, 33H=/1000, 35H=*1000,36H=*100,37H=*10

PC to DPU REQUEST for:

0	1-2	3-4	5-10	11	12	13
01	*	dpu #	*	REQ	Cs	04

REQ=30= STATUS

REQ=31= DOSE or TOTAL

REQ=32= RATE

REQ=39= BackGround

REQ=41= RATE & DOSE

REQ=42= FW version

REQ=43= THR.

DPU to PC answerr

STATUS

0	1-2	3-4	5	6	7	8	9	10	11
01	dpu #	30	31	39	69=i	6E=	73=	74=t	33= rotem
						n	S		

	13					
73=	74=t	61=a	30	30	Cs	04
S						

DOSE or TOTAL & RATE & BackGround & THR & VERTION

0	1-2	3-4	5-6	7-11
01	dpu #	30	32 35	meter reading

12	13- 17	18	19	20	21	22	23	24
Ехр	Unit	R	Det	61=	ST1	ST2	Cs	04
		q		а				

RATE&DOSE

0	1-2	3-4	5-6	7-11	12	13-17
01	dpu #	30	33, 36	Rate	Rate	Rate
				reading	Exp	Unit

18	19	20	21	22	23-27	28	29-33	34	35
R	Det	61=	ST1	ST	Dose	Dose	Dose	Cs	04
q		a		2	reading	Exp	Unit		

Byte 7-11: MANTISA READING INCLUDE DP

Byte 12: EXP READING (20H=0, 4BH=K=3, 4DH=M=6, 47H=G=9, 54H=T=12)

DOSE, TOTAL. RATE, THR= MANTISA*10EEXP

BackGround

Byte 7-11 = *10000+*1000+*100+*10+*1

VERTION

Byte 7-12=30H, 30H, 32H, 33H, 39H, 20H = 329

If FAIL FLG **Byte 7-12** = 4EH,61H,20H,20H,20H,20H = Na

Byte 13-17 Real UNIT

mR= 20H,20H,20H,6DH,52H uSv=20H,20H,75H,53H,76H mR/h= 20H,6DH,52H,2FH,68H uSv/h=75H,53H,76H,2FH,68H CPS=20H,20H,43H,50H,53H COUNT=43H,4FH,55H,4EH,54H

Byte18= Rq code

DOSE or TOTAL =31H RATE = 32H BackGround =39H RATE+DOSE=41H VER=42H THR=43H

Detector type Byte19

30-No detector

31-pm10

32-pm11

33- ic10

34-gm10

35-gm40

36-gm41

36-gm41 37-gm42

38- BF3

39-42-30H

41- UR

42- Berthold

Byte21-ST1 IF OVF=31H ELSE 30H
Byte22-ST2 IF FAIL_FLG=34H ELSE 30H

Byte23- CS=0FFFFH-(BYTE1+2.....22)